

Preliminary

Animatics

SmartMotor™

with **DeviceNet**

Specifications:

Appendices

Copyright Animatics 2002, 2003

Revision 0 4/08/03
Revision 1 10/6/03

Jason Hyatt
Jason Hyatt

APPENDIX: I/O POLLING MESSAGE FORMATS

Type 05 hex Torque

[illegible]

Type 1B hex Position Controller Attribute

[illegible]

Preliminary

MOTION RESPONSE MESSAGE TYPES

Type 01 hex Actual Position

Type 02 hex Command Position

Type 03 hex Actual Velocity

Type 04 hex Command Velocity

Type 05 hex Torque

Type 07 hex Captured Index Position

Response Message Format

Byte	Bit 7	Bit 6	Bit 5	Bit 4	Bit 3	Bit 2	Bit 1	Bit 0
0	Enable	Index Level	n/a	Current Direction	General Fault	n/a	n/a	Profile in Progress
1	Not Used By SmartMotor™							
2	Load Complete	n/a	FE Fault	n/a	n/a	Rev Limit	Fwd Limit	n/a
3	Not Used By SmartMotor™			Response Message Type				
4	Response Data 0 (Least Significant)							
5	Response Data 1							
6	Response Data 2							
7	Response Data 3 (Most Significant)							

ERROR RESPONSE MESSAGE TYPE

Type 14 hex Command/Response Error

Response Message Format

Byte	Bit 7	Bit 6	Bit 5	Bit 4	Bit 3	Bit 2	Bit 1	Bit 0
0	Enable	Index Level	n/a	Current Direction	General Fault	n/a	n/a	Profile in Progress
1	Reserved = 0							
2	Load Complete	n/a	FE Fault	n/a	n/a	Rev Limit	Fwd Limit	n/a
3	Not Used By SmartMotor™			Response Message Type				
4	General Error Code							
5	Additional Code							
6	Copy of Command Message Data Byte 2							
7	Copy of Command Message Data Byte 3							

Preliminary

ATTRIBUTE RESPONSE MESSAGE TYPES

Type 1A hex Position Controller Supervisor Attribute

Type 1B hex Position Controller Attribute

Response Message Format

Byte	Bit 7	Bit 6	Bit 5	Bit 4	Bit 3	Bit 2	Bit 1	Bit 0
0	Enable	Index Level	n/a	Current Direction	General Fault	n/a	n/a	Profile in Progress
1	Attribute Number to GET							
2	Load Complete	n/a	FE Fault	n/a	n/a	Rev Limit	Fwd Limit	n/a
3	Not Used By SmartMotor™			Response Message Type				
4	Response Data 0 (Least Significant)							
5	Response Data 1							
6	Response Data 2							
7	Response Data 3 (Most Significant)							

Preliminary

APPENDIX: SAMPLE USING I/O MESSAGING

POSITION MODE (assuming acceleration and velocity have already been set)

Command Message 8 byte payload

80 00 01 01 01 02 00 00

Meaning

80 Enable

00 unused

01 Command Target Position

01 Request Actual Position Response

01 Target Position LSB = 1

02 Target Position next sig byte = 512

00 Target Position 0

00 Target Position MSB =0

(Target Position = 0+0+1+512 = 513)

Response Message 8 byte payload

80 00 00 01 00 00 00 00

Meaning

80 Enabled

00

00

01 Target Position Response Message

00 Actual Position LSB to MSB = 0

00

00

00

(Actual Position = 0+0+0+0 = 0)

Command Message

81 00 01 01 01 02 00 00

Meaning

81 Enable + **Load Data**

Response Message

Preliminary

Meaning

91 00 **80** 01 00 00 00 00
91 Enabled+**Forward Direction**+**Move Profile in Progress**
00
80 **Data has been Loaded**

Command Message

80 0 01 01 02 00 00

Meaning

80 Enable+clear Load Data to complete handshake, preparing for next command
since Response Message byte 2 bit 7 indicates data has been loaded

Response Message

91 00 00 01 **0A** 00 00 00

Meaning

(Actual Position is $0+0+0+10 = 10$, motor has begun to move)

Command Message

80 00 01 01 01 02 00 00

Response Message

91 00 00 01 **0B** **01** 00 00

Meaning

(Actual Position is $0+0+11+256 = 267$.)

Command Message

80 00 01 01 01 02 00 00

Response Message

80 00 00 01 **01** **02** 00 00

Meaning

80 Enabled+cleared Forward Direction+cleared Move Profile in Progress

(Actual Position is $0+0+1+512 = 513 = \text{Target Position}$)

Preliminary

APPENDIX: CONCISE I/O MESSAGE FORMAT

Command Message Format

All Types

Byte	Bit 7	Bit 6	Bit 5	Bit 4	Bit 3	Bit 2	Bit 1	Bit 0				
0	Enable	Reg Arm	Hard Stop	Smooth Stop	Direct- ion (V mode)	Incre- mental	Start Block*	Load Data/ Start Move Profile				
1	<type specific meaning>											
2	Command Axis*				Command Message Type							
3	<type specific meaning>											
4	Data Value Low Byte											
5	Data Value Low Middle Byte											
6	Data Value High Middle Byte											
7	Data Value High Byte											

Type Specific Byte Meanings

Type 01 hex Target Position

Type 02 hex Target Velocity

Type 03 hex Acceleration

Type 04 hex Deceleration*

Type 05 hex Torque

1	Block Number*							
3	Response Axis*				Response Message Type			

Type 1A hex Position Controller Supervisor Attribute

Type 1B hex Position Controller Attribute

1	Attribute to Get							
3	Attribute to Set							

*(not supported by SmartMotor™)

Preliminary

Response Message Format

All Types

Byte	Bit 7	Bit 6	Bit 5	Bit 4	Bit 3	Bit 2	Bit 1	Bit 0
0	Enable	Reg Level	Home Level*	Current Direction	General Fault	On Target Position*	Block Execution*	Profile in Progress
1	<type specific meaning>							
2	Load Complete	Block Fault*	FE Fault	Neg Limit	Pos Limit	Rev Limit	Fwd Limit	Fault Input Fault*
3	Response Axis*			Response Message Type				
4	Data Value Low Byte							
5	Data Value Low Middle Byte							
6	Data Value High Middle Byte							
7	Data Value High Byte							

Type Specific Byte Meanings

Type 01 hex Actual Position

Type 02 hex Command Position

Type 03 hex Actual Velocity

Type 04 hex Command Velocity

Type 05 hex Torque

Type 07 hex Captured Index Position

1 Block Number*

Type 14 hex Command/Response Error

1 Reserved = 0

4 General Error Code

5 Additional Code

6 Copy of Command Message Byte 2]

7 Copy of Command Message Byte 3

Type 1A hex Position Controller Supervisor Attribute

Type 1B hex Position Controller Attribute

1 Attribute to Get

*(not supported by SmartMotor™)

Preliminary

APPENDIX: OFTEN-USED ATTRIBUTES

Position Controller Supervisor, Class 36 decimal, Instance 1

Attribute ID	Access Rule	Name	DeviceNet Data Type	Description of Attribute	Get Action	Set Action
25	Set	Follow Enable	BOOL	0=disabled 1=enabled	RMODE == F or S or X-> 1	1, <encoder>: MF4 MFR G 1, <step+dir>: MS MSR G 0:
27	Set	Follow Divisor	DINT	Used to calculate the Command Position by dividing the Follow Axis position with this value	a=MFDIV Ra	MFDIV=nnn
28	Set	Follow Multiplier	DINT	Used to calculate the Command Position by dividing the Follow Axis position with this value	a=MFMUL Ra	MFMUL=nnn
100	Set	Follow Type	USINT	0=Step+Dir 1=Encoder		

Position Controller, Class 37 decimal Instance 1

Attribute ID	Access Rule	Name	DeviceNet Data Type	Description of Attribute	Get Action	Set Action
3	Set	Mode	USINT	Operating Mode	RMODE , P/R=0, V=1, T=2	0: MP 1: MV 2: MT
6	Set	Target Position	DINT	Position value to set		absolute: P=nnn incremental: D=nnn
7	Set	Target Velocity	DINT	Velocity value to set	RV	V=nnn
8	Set	Acceleration	DINT	Acceleration rate	RA	A=nnn
10	Set	Incremental Position Flag	BOOL	0=absolute, 1=incremental		
11	Set	Load Data/ Start Profile/ Profile in Progress	BOOL	On set, loads data and starts the current profile. On get, reports Profile in Progress	RW status bit 0	1: G 0: N/A
13	Set	Actual Position	DINT	Actual absolute position. Set to redefine actual position.	RP (or RPW)	O=nnn

Preliminary

Attribute ID	Access Rule	Name	DeviceNet Data Type	Description of Attribute	Get Action	Set Action
14	Get	Actual Velocity	DINT	Reports actual velocity	RV (only valid in Torque Mode)	N/A
15	Get	Commanded Position	DINT	The instantaneous calculated position	RP (or RPW) + RPE	N/A
16	Get	Commanded Velocity	DINT	The instantaneous calculated velocity	RV	N/A
17	Set	Enable	BOOL	0=disable 1=enable		1: G or MP D=0 G, allow G or MT 0: OFF
20	Set	Smooth Stop	BOOL	Smooth Stop motor	0	1: X
21	Set	Hard Stop	BOOL	Hard Stop motor	0	1: S
23	Set	Direction	BOOL	Instantaneous Direction 0=reverse, 1=forward	Position Mode (direction of move) Velocity Mode (sign of Velocity). Torque Mode, sign of Torque	V=+/-nnn G T=+/-nnn
25	Set	Torque	DINT	Output Torque	RT	T=nnn or T=-nnn
47	Set	Following Error Fault	BOOL	Following error occurrence flag	RW status bit 5	
48	Get	Actual Following Error	DINT	Actual Following error	RPE	N/A
58	Get	Load Data Complete	BOOL	valid data for a valid I/O command message type has been loaded into the position controller		N/A
100	Set	Current Limit	DINT	Current limit of motor 0 to 1023	RAMPS	AMPS=nnn

Preliminary

APPENDIX: Identity Object: ID and Versions

The Identity Object is object class hex 01. It has a single instance, instance 1.

CLASS 01 INSTANCE 1

Attribute ID	Access Rule	Name	Device Net Data Type	Description
1	GET	Vendor ID	UINT	Vendor number, ODVA -assigned in SYCON software Get Attribute dialog box, this is displayed as two hex bytes, 2 hex digits per byte, low order byte first. $\begin{array}{rcl} 2A03 \text{ is } 03 * 256 & = & 768 \\ 2*16 & = & 32 \\ A * 1 & = & 10 \\ \hline & & 810 \end{array}$

(a few original units used $1101 = 273$)

4	GET	Revision	STRUCT USINT major revision USINT minor revision
---	-----	----------	--

in SYCON software Get Attribute dialog box this is displayed
as two hex bytes, 2 hex digits per byte, major revision first.

for example:

0105 is major revision 1 minor revision 3